WI-CAMS and RapidTAG User Guide

January 17, 2018



Table of Contents

RapidTAG: An overview
RapidTAG with internet4
RapidTAG setup with internet4
Configuring RapidTAG with internet5
Merging RapidTAG with other Salamander solutions7
RapidTAG without internet7
RapidTAG setup without internet7
Configuring RapidTAG without internet8
Printing RapidTAG badges10
RapidTAG with a driver's license10
RapidTAG with manual entries11
Closing out of RapidTAG12
Troubleshooting13
Troubleshooting the USB scanner13
Troubleshooting the Zebra printer14

RapidTAG: An overview

RapidTAG is an on-scene badging solution supported by Salamander Technologies. RapidTAG accounts for non-credentialed responders with a temporary deliverable. Personnel are temporarily added to the Salamander exchange platform and subject to the same accountability functions as state-credentialed assets (e.g. timestamps, branch assignments, etc.).

Like all elements in WI-CAMS (Wisconsin Credentialing and Asset Management System), state policy directs agencies using RapidTAG to use a standardized template for temporary deliverables. This design standard comes pre-installed on every WEM-managed RapidTAG kit.

RapidTAG can be used in conjunction with other Salamander Technologies products. This kit includes instructions for 02 TRACK, which allows users to scan both permanent and temporary deliverables on a tablet or smartphone. Additional documentation on WI-CAMS-supported solutions can be found in the "User Tools" section at wicams.wi.gov.

RapidTAG kits are available to local and state agencies as resources for request through Wisconsin's 24-Hour Duty Officer: 1-800-943-0003

RapidTAG with internet

RapidTAG setup with internet

While the RapidTAG case is water-proof, the equipment inside it is not. Prior to setup, verify that the RapidTAG equipment is in a dry location.

- 1. Power on the RapidTAG kit's laptop and log into Windows with a DMA-issued profile. If you have not yet been issued a profile, you can submit a request to <u>wicams@wisconsin.gov</u>.
- 2. Verify that the laptop has an established internet connection. If no connection seems present, confirm that the laptop's network adapters have been turned on. Whenever possible, the network connection should always be secure.
- 3. Plug in the tethered scanner to one of the laptop's USB ports. The scanner should "beep" once it is recognized by Windows. Refer to the "Troubleshooting the USB scanner" section for additional assistance.
- 4. Connect the Zebra GX430t printer to a power source. Plug in the printer to another of the laptop's USB ports. Flip on the power switch at the back of the printer. Refer to the "Troubleshooting the Zebra printer" section for additional assistance.

Configuring RapidTAG with internet

- 1. Once you have verified the laptop has a network connection, click the RapidTAG icon on the desktop.
- 2. You may be prompted with a Windows administrator message. Click "No" and proceed.
- 3. From the RapidTAG main screen, click "File" and then "Options."
- 4. Select the "Organization" tab and verify the following settings.

PrapidTAG	OPTIONS
Server Organ	nization Scanners Printing Time Assignment
*Name	WI Emergency Management
*Code	WIE550WEM0
*Туре	Emergency Management Agency -
*Country	United States -
*State	Wisconsin -

- 5. Select the "Scanners" tab, and confirm that "USB scanners" is enabled.
- 6. Click "USB Scanners" and verify that the USB device is named and that "Use Device" and "Connected" are both set to "Yes." Click "Close," or refer to the "Troubleshooting the USB scanner" section for additional assistance.

USB Settings					
CLOSE TEST SAVE	REFRESH DELETE	USB S	SETTINGS		
Name Ty	pe Use Dev	Connected	Available	Device	
USB Scanner Sc	anner Yes	Yes	Untested	HID\\VID_05E0&PIC	_1300\\7&36DFFED2&
•	m				•
Device Name					🗹 Auto Load
Device Type	Scanner			•	
					.:

7. Click the "Printing" tab, and verify the following settings. Click "Save" and "Back."

(rapidTAG	×
BACK SAVE	OPTIONS
Server	Organization Scanners Printing Time Assignment
Con No	mpany Equipment Design No Design
Res ID	sponders Card 2016_Temporary
Printer	ZDesigner GX430t
Design	ID Card 2016_Temporary
Copies	1 Starting Record Number 1
Output T	Type Auto Print 🔹
	Output Company Members

Merging RapidTAG with other Salamander solutions

Now that you have properly configured RapidTAG, you may also merge its data with data from an 02 TRACK or Command solution -- provided you are also using those products. Refer to the "Merging incident data in 02 TRACK" section in the "WI-CAMS and 02 TRACK User Guide" for more information.

RapidTAG without internet

RapidTAG setup without internet

While the RapidTAG case is water-proof, the equipment inside it is not. Prior to setup, verify that the RapidTAG equipment is in a dry location.

- 1. Power on the RapidTAG kit's laptop and log into Windows with a DMA-issued profile. If you have not yet been issued a profile, you can submit a request to <u>wicams@wisconsin.gov</u>.
- 2. Plug in the tethered scanner to one of the laptop's USB ports. The scanner should "beep" once it is recognized by Windows. Refer to the "Troubleshooting the USB scanner" section for additional assistance.
- 3. Connect the Zebra GX430t printer to a power source. Plug in the printer to another of the laptop's USB ports. Flip on the power switch at the back of the printer. Refer to the "Troubleshooting the Zebra printer" section for additional assistance.

Configuring RapidTAG without internet

Because you will be using RapidTAG without a wireless connection, you will <u>not</u> be able to join RapidTAG data with data from other computer-based solutions. The software may occasionally remind you of this. Simply close out of the prompt and resume operations.

() Error	8
There was a problem sending data to Salamander Live. Please try	again later.
More >>	Close

- 1. Click the RapidTAG icon on the desktop.
- 2. You may be prompted with a Windows administrator message. Click "No" and proceed.
- 3. From the RapidTAG main screen, click "File" and then "Options."
- 4. Select the "Scanners" tab, and confirm that "USB scanners" is enabled.
- 5. Click "USB Scanners" and verify the three settings below are all set to "Yes." Click "Close."

USB Settings					
CLOSE TEST SAVE	REFRESH DELETE	USB SETTI	NGS		
Name	Type Use Devic	e Connected	Available	Device	
Tethered Scanner	Scanner Yes	Yes	Yes	HID\\VID_05	E0&PID_1300\\7&CE06F
٢	m				4
Device Name	Tethered Scanner				Auto Load
Device Type	Scanner			•	
Device connected success	fully.				

6. Click the "Printing" tab, and verify the following settings. Click "Save" and "Back."

(rapidTAG	×
Dack Save	OPTIONS
Server	Organization Scanners Printing Time Assignment
Cor No	Design Equipment No Design
ID Res	sponders Card 2016_Temporary
Printer	ZDesigner GX430t
Design	ID Card 2016_Temporary
Copies	1 Starting Record Number 1
Output T	Type Auto Print
	Output Company Members

Printing RapidTAG badges

Before responder badges can be printed, RapidTAG requires any personnel you add to be associated with an organization.

- 1. If the incident in RapidTAG has not been started yet, click "Start" in the RapidTAG main screen.
- 2. Click the "Organization" tab and then click "Add."
- 3. Fill in the appropriate fields. Note that the ID field will auto-populate. Since temporary badges are not added to the statewide WI-CAMS database, you can leave the information in this field as is. Click "Finish."
- 4. This organization will now be available to you when printing temporary badges. Repeat these steps for every organization required.

RapidTAG can print temporary badges by scanning a driver's license or via manually entering data. Instructions on both methods are as follows:

RapidTAG with a driver's license

- 1. If the incident in RapidTAG has not been started yet, click "Start" in the RapidTAG main screen.
- 2. Verify the "People" tab is selected. With the USB Scanner, scan the barcode on a driver's license. Depending on the license, you may need to hold down the scanning function for several seconds before the barcode is recognized.

		Perso	n	
ID	171025162029456	Organization	WI Emergency Management	• New
Last Name	Doe	First Name	John	
Title	State Duty Officer	- Birth Date	☑ 5/25/1977	
Assignment	Checked In	 Expires 	☑ 10/25/2017	
Role		- Location		•
	Qualifications		Selected Qualifications	
			Selected Qualifications	
Code Descri	iption	>>>	Code Description	

3. The following screen will appear:

- 4. Fill fields as needed. First Name, Last Name, and Organization are all required.
- 5. Select the organization from the existing dropdown list. You may also go back and add in a new organization using the above steps.
- 6. Verify the "Print when finished" checkbox is checked. Per WI-CAMS policy, the badge's expiration must not exceed 72 hours from the date/time of printing.
- 7. Click "Finish" or press the "Enter" key to print. Your RapidTAG badge can now be scanned and tracked through the Salamander exchange platform. (Note: You must do so through an O2 TRACK device or handheld scanner. This kit's USB scanner is <u>not</u> for scanning WI-CAMS deliverables.)

RapidTAG with manual entries

- 1. If the incident in RapidTAG has not been started yet, click "Start" in the RapidTAG main screen.
- 2. Verify the "People" tab is selected. To add a responder, click "Add," and fill fields as needed. First Name, Last Name, and Organization are all required.
- 3. Select the organization from the existing dropdown list. You may also go back and add in a new organization using the above steps.
- 4. Click "Finish" or press the "Enter" key to print. Your printed RapidTAG badge can now be scanned and tracked through the Salamander exchange platform. (*Note: You must do so through an 02 TRACK device or handheld scanner. This kit's USB scanner is <u>not for scanning WI-CAMS deliverables.</u>)*

Closing out of RapidTAG

- 1. When your incident has ended, you will need to close out of RapidTAG and power down the hardware. From the RapidTAG main screen, click "End." The software may prompt you to confirm this action.
- 2. Close out of the RapidTAG software, and power down the laptop.
- 3. Disconnect all power adapters. Re-wind all chords and return equipment pieces to their original locations in the RapidTAG case. Refer to the diagram included in the kit if needed.
- 4. If not yet filled out, complete the equipment checkout form enclosed in the kit.

Troubleshooting

Troubleshooting the USB scanner

If the USB scanner's settings are not correct or if the USB scanner will not recognize barcodes, the hardware will need to be calibrated.

- 1. From the main RapidTAG screen, click "Options" and select the "Scanners" tab.
- 2. Confirm that "USB scanners" is checked. Click "USB Scanners."
- 3. Highlight your scanner, and click "Test."
- 4. Scan the back of a driver's license until a window prompt appears. Close out of the prompt.
- 5. Verify that "Tested" now appears under "Available."
- 6. Enter a name for the scanner under "Device Name."
- 7. Check the "Auto Load" checkbox.
- 8. Verify the USB Settings now match the settings below. Note that "Connected" and "Use Device" should now both be set to "Yes."

U	SB Settings										
	CLOSE TEST	O SAVE	REFRE	SH DELE	TE	USB :	SETTINGS				
	Name	Тур	e	Use De	ev	Connected	Available	Device			
	USB Scanner	r Sca	nner	Yes		Yes	Untested	HID\\VID_05E0	&PID_1300	\7&36DFFE	28
	•			1							4
	Device Nar	ne							V	Auto Load	
	Device Typ	e	Scan	ner				•			

- 9. Click "Save" and then click "Close."
- 10. If problems persist, completely remove the USB Scanner by clicking "Delete" in the USB Settings. Unplug the scanner, plug it in once more, and repeat the above steps.
- 11. If problems still persist, send a support request to <u>wicams@wisconsin.gov</u>.

Troubleshooting the Zebra printer

If you have powered on the Zebra printer and the diagnostic light is not a solid green, the printer will need to be adjusted.

- 1. Squeeze both side tabs of the Zebra printer to open the printer lid.
- 2. Verify that the RapidTAG print stock is resting evenly on both of the printer's spools. The stock's justification cannot slant to one side.



3. Once the stock has been readjusted, close the printer lid and press the ream button to ready the print stock.



4. If the diagnostic light is still not a solid green, power-cycle the printer and repeat the above steps. If problems persist, send a support request to <u>wicams@wisconsin.gov</u>.

If the Zebra printer's diagnostic light is a solid green but is rendering a missing or incomplete image, the printer's settings will need to be adjusted in Windows.

- 1. From the Control Panel, select "Devices and Printers."
- 2. Locate the ZDesigner GX430t printer. The connected printer should have an opaque icon with a green checkmark next to it.



- 3. Right-click the printer and select "Printing Preferences."
- 4. Select the "Options" tab and verify the following settings.

	Barcode Font	s			Comm	nand F	onts	
Custom	Commands	Impor	t/Export	setting	3	Tools		About
Options	Advanced	Setup	Dithe	ring	Stocks	3	Printe	er Memory
Settinas								
	No. Of Copies:	Ī	1]			
	Speed:		4		• "/s			
	Darkness:		15		•			
	Stocks:		User def	ined				•
Paper Fo	omat ———							
	🔘 cm			oproximation	trait			
	🔘 mm	9,075	9421	🔘 lan	dscape			
	inch		NBA.	📃 rota	ate 180°			
Size —				_				
	Width:	3.00						
	Height:	5.00						
Unprinta	ble Area ——	-						
-	Left:	0.00		Top:		0.0	0	
	Right:	0.00		Bottor	n:	0.0	0	
				_				

5. Select the "Advanced Setup" tab and verify the following settings.

Barcode Fonts	3			Co	mmano	d Fonte	3
Custom Commands	Import	/Expo	rt setting	js	Too	ls	About
Options Advanced	Setup	Dith	ering	Sto	cks	Print	ter Memory
Use printer settings							
Operation Mode							
Tear off			R	FID			
Rewind			0	utter			
Peel Off			Grou	ıp Qu	antity:	0	
Applicator			() A	dvan	ced **		
Stream			_				
Mirror Image				iverse	e		
Media Type							
Thermal Tra	nsfer		© T	hema	al Direc	t	
Tracking Mode							
Continuous			ON	lark S	Sensing		
Web Sensin	g						
Adjustment							
Тор	0.00	D	inch				
Tear Off	0.00	D	inch				
Left Position	0.00	D	inch				
** Only valid for use with	h Labelin	ng Soft	ware				
Applica	tor		Other			Calib	orate

6. Click "OK." If problems persist, send a support request to <u>wicams@wisconsin.gov</u>.